


Precitec Macro Documentation

05 Line Detection

■ Changelog

Date	Version	Autor	Tested on	Description
2023-03-03	A	Abt	5.19.13	New documentation

■ Description




G01 Line Detection

Turns user Parameter into constant value data stream.

I1: Img
I2: ROI
O1: Pos x_1 [px]
O2: Pos y_1 [px]
O3: Pos x_1 for Scanner
O4: Pos y_1 for Scanner
O1: Pos x_2 [px]
O2: Pos y_2 [px]
O3: Pos x_2 for Scanner
O4: Pos y_2 for Scanner
O9: Angle

■ Macro structure



■ Parameter

NAME	VALUE	Description	UserLevel
00 "0" if < 45deg "1" if > 45 deg → Number	0	Switch ON / OFF	Admin
01 AdjustContrast → Operation	BinarizeIn	Adjusting Contrast	Admin
02 AdjustContrast Min. → Number	32	Minimum contrast	Admin
03 AdjustContrast Max. → Number	1	Maximum contrast	Admin
04 Morphology → Operation	Closing	Closing black pixel into white pixel	Admin
04 Morphology → Number of operations	8	Value of operations	Admin
05 ParallelMaximumOriented → Horizontal main direction	ON	Switch direction	Admin
05 ParallelMaximumOriented → HandleTransposeln	OFF	Switch direction	Admin

05 ParallelMaximumOriented → Resolution in X direction	1	Filterlength in X	Admin
05 ParallelMaximumOriented → Resolution in Y direction	1	Filterlength in Y	Admin
05 ParallelMaximumOriented → Threshold	30	Treshold of operations	Admin
05 ParallelMaximumOriented → Subroi dilation	1		Admin
05 ParallelMaximumOriented → Fine tracking enabled	On	Switch Fine tracking	Admin
05 ParallelMaximumOriented → Maximal line width	20	Defines your maximal line width	Admin
06 CloseGaps → Minimal segment lenth	75	Defines your minimal Linelength	Admin
06 CloseGaps → Max. jump Y	15	Maximal jump of length	Admin
06 CloseGaps → Maximal interpolation	10	Maximal interpolation	Admin
07 Intersect2Lines → Precitec.Filter.Attribute.Intersect2Lines	Off	Switch to Show Angle	Admin