




## 2 - S42 ROI Grey based on Ablation

### ■ Description

Definition of the rectangle of the ROI (**R**egion **O**f Interest) for the grey image seam search, centered in the found ablation zone. Offsets left and right shift the ROI borders left and right fix for the new grey ROI.

### ■ Icon



2 S42 ROI Grey based on Ablation

dynamic grey ROI based on found outside ablation borders

### ■ Parameters

Filters of  
2 S42 ROI Grey based on Ablation



01 ROI grey centered



01.1 Offset left



01.2 Offset right



01.3 min. width



92 Plaus. min. ROI Height


**Attributes of**  
**01 ROI grey centered**

Verbosity level  
 None

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.

### Verbosity example:

The magenta rectangle shows the ROI position where to search for the weld seam. The width and height are given by the ablation ROI width and height (set in subgraph "2 S40").



**Attributes of**  
**01.1 Offset left**

Number  
 20,000

Parameter	Comment
Number	Shifts the left ROI border away from the left ablation zone border towards the seam. [Pixel]

**Attributes of**  
**01.2 Offset right**


Number  
 20,000

Parameter	Comment
Number	Shifts the right ROI border away from the right ablation zone border towards the seam. [Pixel]



### Explanation example of “Offset”:

The yellow arrows show the “offset” on the left side, the magenta arrows show the “offset” on the right side for the ROI where to search for the weld seam.



**Attributes of**  
 01.3 min. width

Number

Parameter	Comment
Number	Threshold for the minimum ROI width, considering the left and right offset values. Lower than the threshold, the ROI is invalid. [Pixel]

**Attributes of**  
 92 Plaus. min. ROI Height

Number

Parameter	Comment
Number	Threshold for the minimum ROI height of plausibility check. Lower than the threshold, the ROI is invalid. [Pixel]





### ■ Measured values for plotter

730	0/1	ROI grey valid
-----	-----	----------------

- **Subgraphs interface**

## IN bridges

## OUT bridges

 <b>image</b>	Img	 <b>image</b>	ROI grey
 <b>value</b>	ROI ablation Y / H Ablation out X left Ablation out X right	 <b>value</b>	ROI grey X / Y / W / H ROI grey valid

- **Graph block diagram**

