



Special – NGS1_A_nn


■ Description

Definition of two rectangles of ROI (**R**egion **O**f **I**nterest) to detect the left resp. right laser line start at the image border. On the left and right side of the the found laser line

- a horizontal LineFit is done to calculate the vertical positions
- a dynamic ROI is placed (on the line) where the intensity of the laser line is measured (plausibility check)
- above the laser line a dynamic ROI is placed where the intensity on the blank is measured as a reference for the binarization in the following subgraphs
- relative to the two vertical positions and with a width value the "Line ROI" is placed where in subgraph NGS1_B the gap is searched for

nn: declaration of the actual subgraph version (here: version 13).

■ Icon



NGS1_A_13

Comment for the new graph

■ Parameters

Filter Groups of NGS1_A_13

G02 ROIs Z position

G05 ROI line

G10 ROIs light laser line

G12 ROIs light background for binarization

G02 ROIs Z position

Filters of
G02 ROIs Z position

P01 ROI Z dz

P02 ROI Z w

P03 ROI Z L

P04 ROI Z R

P05 LineExtraction L

P06 LineExtraction R

P07 LineFit L

P08 LineFit R

P09 lowPass ROline Z

P10 lowPass ROline H

Attributes of
P01 ROI Z dz

Number

100.000

Parameter	Comment
Number	Distance from the upper image rim to the upper ROI rim to detect (vertically) the laser line start, resp. distance from the lower image rim to the lower ROI rim to detect (vertically) the laser line start. [Pixel]

Attributes of
P02 ROI Z w

Number

100.000

Parameter	Comment
Number	Width of the ROI to detect the (vertical) laser line start, with the search starting on the left resp. right image rim. [Pixel]



Attributes of P03 ROI Z L

Verbosity level
 Low

Attributes of P04 ROI Z R

Verbosity level
 Low

Parameter	Comment
Verbosity level	<p>Selection of verbosity level. Larger verbosity levels offer more overlay information.</p> <p>Display of the left resp. right ROI area for the (vertical) detection of the laserline start as a red rectangle.</p> <p>Also drawn is the ROI area for the "Reference intensity on the laser line" of "G10 ROIs light laser line" as a green rectangle.</p> <p>Also drawn is the ROI area for the "Reference intensity on the blank" of "G12 ROIs light background for binarization" as a green rectangle.</p>

Attributes of P05 LineExtraction L

Verbosity level
 None

Tracking Threshold
 80

Double Tracking bool
 1

mean x pixel
 3

search area y upper pixel
 3

mean area y pixel
 5

Maximum Gap Width
 9

Maximum Number of Gaps
 17

Maximum height jump
 3

Starting Point Width Pixel
 10

Starting Point Height Pixel
 10

Attributes of P06 LineExtraction R

Verbosity level
 None

Trackstart
 0

Tracking Threshold
 80

Double Tracking bool
 1

mean x pixel
 3

search area y upper pixel
 3

mean area y pixel
 5

Maximum Gap Width
 9

Maximum Number of Gaps
 17

Maximum height jump
 3

Starting Point Width Pixel
 10

Starting Point Height Pixel
 10

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Trackstart	If the "DoubleTracking" is off: 0 The laser line tracking is done from left to right. 1 The laser line tracking is done from right to left.
Tracking threshold	Minimum grey scale value for an image pixel that it's defined to belong to the laser line. [Greylevel]
DoubleTracking	0 The laser line is searched from left to right. 1 The laser line is searched from left to right, and then once again from right to left.
mean x	Number of pixels in X direction, used for averaging the brightness in order to define the next point of the laser line. [Pixel]
search area y	This parameter defines the maximum limits for the search area in Y direction, used for searching the next tracking point. [Pixel]
mean area y	Number of pixels in Y direction, over which the "Average brightness in X direction" is averaged, in order to define the next laser line point. [Pixel]
Maximum Gap Width	Maximum allowed width of a laser line interruption: If the number of side by side laying pixels, having a lower grey scale value than the search threshold, exceeds this parameter figure, the line interrupts counter figure is raised by 1. [Pixel]
Maximum Number of Gaps	Maximum number of laser line interrupts: If the number of line interrupts per laser line becomes higher than this parameter, the line search is stopped and a line interrupt warning is released.
Maximum height jump	Maximum interrupt in Y direction: If the height jump of the laser line exceeds this parameter, the line search is stopped. [Pixel]
Starting Point Width	Width of the search area on the left laser line ROI border to find the vertical start position of the laser line. [Pixel]
Starting Point Height	Height of the search area on the left laser line ROI border to find the vertical start position of the laser line. [Pixel]



Attributes of P07 LineFit L

Verbosity level

Low

Attributes of P08 LineFit R

Verbosity level

Low

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information. Marks the start/end position for the linefit on the left side resp. on the right side with small crosses.

Attributes of P09 lowPass ROline Z

Filter length N values

11

Maximal jump.

100,000.000

Parameter	Comment
Filter length	Filtering of the vertical positions of the found laser line points.
Maximal jump	Max. allowed distance of the new position to the filtered position that the new position is taken over into the filter. [Pixel]

Attributes of P10 lowPass ROline H

Filter length N values

11

Maximal jump.

100,000.000

Parameter	Comment
Filter length	Filtering of the intensity values of the found laser line points.
Maximal jump	Max. allowed difference of the new intensity value to the filtered intensity that the new intensity value is taken over into the filter. [Greylevel]

G05 ROI line

Filters of
G05 ROI line

P01 ROI line dy

P02 ROI line width

P03 ROI line dz upper

P04 ROI line dz lower

P05 ROI line

Attributes of
P01 ROI line dy

Number

125.000

Parameter	Comment
Number	Distance of the "ROI line" for prepositioning from the left image rim. [Pixel]

Attributes of
P02 ROI line width

Number

750.000


Parameter	Comment
Number	Width of the "ROI line" for prepositioning. [Pixel]




**Attributes of
P03 ROI line dz upper**



Number

Parameter	Comment
Number	Distance from the (vertical) image center to the upper rim of the "ROI line" for prepositioning.


**Attributes of
P04 ROI line dz lower**


Number

Parameter	Comment
Number	Distance from the (vertical) image center to the lower rim of the "ROI line" for prepositioning.


**Attributes of
P05 ROI line**



Verbosity level


Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information. Marks the area of the "ROI line" for prepositioning as a white rectangle.


G10 ROIs light laser line

Filters of

G10 ROIs light laser line

 H

 W

 dz

Attributes of

H

Number

12.000

Parameter	Comment
Number	Height of the ROI on the laser line to measure the "Reference intensity on the laser line". [Pixel]

Attributes of

W

Number

50.000

Parameter	Comment
Number	Width of the ROI on the laser line to measure the "Reference intensity on the laser line". [Pixel]

Attributes of

dz

Number

-6.000

Parameter	Comment
Number	Distance from the (vertical) image center to the upper rim of the ROI on the laser line to measure the "Reference intensity on the laser line". [Pixel]



G12 ROIs light background for binarization

Filters of
G12 ROIs light background for binarization

P01 ZoffsetToLine
 P02 H
 P03 LowPass Background light

Attributes of
P01 ZoffsetToLine

Number

Parameter	Comment
Number	Distance from the (vertical) image center to the upper rim of the ROI to measure the "Reference intensity on the blank". [Pixel]

Attributes of
P02 H

Number

Parameter	Comment
Number	Height of the ROI on the laser line to measure the "Reference intensity on the blank". [Pixel]

Attributes of
P03 LowPass Background light

Kind of low pass
 Mean

Filter length N values
 11

Maximal jump.
 100,000,000

Maximal value
☒ On/Off

Parameter	Comment
Kind of low pass	Mean Mean filter over "Filter length" images Median Median filter over "Filter length" images
Filter length	Filtering over the given number of images to smoothen the "Reference intensity on the blank". [Images]
Maximal jump	Max. allowed difference of the new intensity value to the filtered intensity value that the new intensity value is taken over into the filter. [Greylevel]
Maximal value	On "Maximal jump" is considered. Off Switches off "Maximal jump", so any value is taken over.



■ Measured values for plotter

--	--	--


■ Subgraphs interface

IN bridges

OUT bridges

		image value	IMG ROLline Zpx left / right Zpx upper / lower HeightDifference raw mm PartIntensity
--	--	----------------------------------	---

■ Graph block diagram



The figure illustrates two parallel processing streams. The left stream (dorsal) processes spatial information: it starts with a 'dy' block, followed by a 'dx' block, then a 'dz' block. These are combined with 'Zpos L' and 'Zpos R' inputs to calculate 'Ypos ROIs left' and 'Ypos ROIs right'. The right stream (ventral) processes color information: it starts with a 'DynamicColor' block, followed by a 'MeanBrightness' block, and finally a 'No Check' block to produce 'PureResult'. The 'DynamicColor' block receives inputs from 'Rpos', 'Gpos', 'Bpos', and 'H ROI right laserline'.

