


2 - S40 SEARCH Ablation borders Grad Simple

Description


Searches the left/right border of the ablation zone inside a given rectangle out of the grey intensity image. The ablation zone is normally visible as a dark vertical band on the blanks.

The rectangle of the ROI (Region Of Interest) is cut in small horizontal stripes. In each stripe a left and right ablation border position is searched. The average over all positions gives the final position for the left and for the right border position.

Icon




Parameters






Parameter	Comment	
Number	Height of each stripe in the ROI where to search for left/right side ablation border position. [Pixel]	



Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Filter length	The noisier the brightness is, the higher this parameter must be selected (1 - 100). This smoothens the brightness in every stripe before further processing, using a Median filter. [Pixel]





Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Filter length	The noisier the brightness is, the higher this parameter must be selected (1 - 100). This smoothens the brightness in every stripe before further processing, using a Mean filter. [Pixel]



Verbosity example:

The orange lines represent the intensity shape in each stripe of the ROI with the upper ablation ROI border as "intensity zero" reference.






Parameter	Comment	
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.	
Filter length	Filter length for the gradients in each stripe, to be averaged on. [Pixel]	

Verbosity example:

The orange lines represent the intensity changes (gradients) in each stripe of the ROI with the upper ablation ROI border as "Gradient zero" reference.






Parameter	Comment	
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.	

Verbosity example:

Yellow crosses mark the found left ablation border position in every stripe of the ROI. Yellow lines mark found points that were changed/eliminated.

Magenta crosses mark the found right ablation border position in every stripe of the ROI. Magenta lines mark found points that were changed/eliminated.





Parameter	meter Comment	
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.	

Measured values for plotter



Subgraphs interface

IN bridges OUT bridges

■ image	Img ROI ablation	 value	Ablation out X left Ablation out X right
☑ value	ROI ablation Y ROI ablation H		

■ Graph block diagram

