




2 - S12 ROI Grey



■ Description

Definition of the rectangle of the ROI (**R**egion **O**f Interest) for the grey image seam search and analysis with a fixed position over all images of the seam.

■ Icon




■ Parameters



Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
ROI Position X	Start position X of the rectangle (ROI). [Pixel]
ROI Position Y	Start position Y of the rectangle (ROI). [Pixel]
Width	Width of the rectangle (ROI). [Pixel]
Height	Height of the rectangle (ROI). [Pixel]


Verbosity example:

The green rectangle shows the set grey image ROI.





Note:

If the displayed green rectangle is only a small horizontal line then the parameters of subgraph "1 S10 Camera with StartEnd" should be checked!






Attributes of
92 Plaus. min. ROI Height


Number

Parameter	Comment
Number	Threshold for the minimum ROI height of plausibility check. If the set value is lower than the threshold, the ROI is invalid. [Pixel]

■ Measured values for plotter

730	0/1	ROI grey valid
-----	-----	----------------

■ Subgraphs interface

IN bridges

OUT bridges

 image	Img	 image	ROI grey
 start end info	Start end info	 value	ROI grey X / Y / W / H ROI grey valid

■ Graph block diagram

