


2 - S41 ROI Line based on Ablation


Description


Definition of the rectangle of the ROI (Region Of Interest) for the laser line search. This ROI will be automatically centered in the found ablation zone

Icon



Parameters






Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
ROI Position X	Start position X of the rectangle (ROI). [Pixel]
ROI Position Y	Start position Y of the rectangle (ROI). [Pixel]
Width	Width of the rectangle (ROI). [Pixel]
Height	Height of the rectangle (ROI). [Pixel]

Verbosity example:

The blue rectangle shows the set ROI where to search for the laser line. It's small to avoid the gaps visible at the ablation area borders.








Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.

Verbosity example:

The magenta rectangle shows the ROI after it's horizontally centered inside the found ablation area.





Parameter	Comment
Number	Threshold for the minimum ROI height of plausibility check. Lower than the threshold, the ROI is invalid. [Pixel]

Measured values for plotter

729	0/1	ROI line valid
120	0/ 1	Not mile valid

Subgraphs interface

IN bridges

■ image	Img	■ image	ROI line
☑ value	Ablation out X left Ablation out X right	☑ value	ROI line X / Y / W / H ROI line valid
	Start end info		

OUT bridges

■ Graph block diagram

