




## 5 - S91 CALC Ablation width V2



### ■ Description

Measure left and right ablation width.

### ■ Icon



### ■ Parameters



Parameter	Comment
Filter length	Number of camera images to average the measured ablation width on the left side of the seam. [Images].

Attributes of

12 Averaging Ablation width right

Filter length

N values




1

Parameter	Comment
Filter length	Number of camera images to average the measured ablation width on the right side of the seam. [Images].

Measured values for plotter

589	0 ... xxx	Width ablation left
590	0 ... xxx	Width ablation right

Subgraphs interface

IN bridges		OUT bridges	
 image	Img	 value	Ablation width left Ablation width right
 value	Seam pos left filtered Seam pos right filtered ROI grey valid Ablation out X left Ablation out X right		



## ■ Graph block diagram

