




5 - S92 CALC Ablation intensity

■ Description

Measures on the left and right side of the seam the mean intensity in the ablation zone. The therefore used "intensity" ROIs (**R**egion **O**f **I**nterest) are fix in size and linked to the seam borders.

The intensity ROIs are divided in boxes/tiles. In each box/tile the surface characteristics will be calculated and classified.

■ Icon



5 S92 CALC Ablation intensity

Measure left and right Intensity of ablation zone. Intensity ROIs are fix and linked to the inside ablation borders.

■ Parameters

Filter Groups of 5 S92 CALC Ablation intensity



G00 SYS PARAMETER INITIAL SETUP Intensity


G30 Mean Intensity Ablation


G31 Local Intensity fault


G61 ROI Intensity Ablation


G00 SYS PARAMETER INITIAL SETUP intensity


Filters of
G00 SYS PARAMETER INITIAL SETUP Intensity


 00 ROI height left/right

 01 ROI offset Y left/right

 02 ROI width left

 03 ROI offset from gap left

 12 ROI width right

 13 ROI offset from gap right

 **Attributes of**
00 ROI height left/right

Number



Parameter	Comment
Number	Height of the intensity ROI left and right. [Pixel]

 **Attributes of**
01 ROI offset Y left/right

Number

Parameter	Comment
Number	Number of pixels to shift the intensity ROI in Y direction (vertical). The center of the intensity ROI is vertically centered in the ablation ROI. [Pixel]




**Attributes of
02 ROI width left**




Number

Parameter	Comment
Number	Width of the left intensity ROI. [Pixel]


**Attributes of
03 ROI offset from gap left**


Number

Parameter	Comment
Number	Horizontal distance of the left intensity ROI from the left seam border. [Pixel]


**Attributes of
12 ROI width right**


Number

Parameter	Comment
Number	Width of the right intensity ROI. [Pixel]


**Attributes of
13 ROI offset from gap right**


Number

Parameter	Comment
Number	Horizontal distance of the right intensity ROI from the right seam border. [Pixel]

G30 Mean Intensity Ablation

Filters of

G30 Mean Intensity Ablation

11 Averaging Mean intensity left

Attributes of

11 Averaging Mean intensity left

Filter length

1

N values

Parameter	Comment
Filter length	Pixel resolution in X and Y for the mean intensity. [Pixel]

G31 Local Intensity fault

Filters of

G31 Local Intensity fault

01 Surface Mean intensity left

02 Surface Classifier left

11 Surface Mean intensity right

12 Surface Classifier right



Attributes of
01 Surface Mean Intensity left

Tiles Width pixels

Horizontal Jump pixels

Tiles Height pixels

Vertical Jump pixels

Parameter	Comment
Tiles Width	Width of a box/tile for detailed analysis. [Pixel]
Horizontal Jump	Horizontal distance from tile to tile. [Pixel]
Tiles Height	Height of the box/tile for detailed analysis. [Pixel]
Vertical Jump	Vertical distance from tile to tile. [Pixel]

Attributes of
02 Surface Classifier left

Verbosity level

Maximal Mean

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Maximal Mean	Max. allowed mean box/tile intensity. [Greylevel]

Tiles Width

—

20 (200)

+

pixels

Horizontal Jump

—

20 (200)

+

pixels

Tiles Height

—

20 (200)

+

pixels

Vertical Jump

—

20 (200)

+

pixels

Parameter	Comment
Tiles Width	Width of the box/tile for detailed analysis. [Pixel]
Horizontal Jump	Horizontal distance from tile to tile. [Pixel]
Tiles Height	Height of the box/tile for detailed analysis. [Pixel]
Vertical Jump	Vertical distance from tile to tile. [Pixel]

Verbosity level

None

⬆

Maximal Mean



135.000

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Maximal Mean	Max. allowed mean box/tile intensity. [Greylevel]



G61 ROI Intensity Ablation

Filters of
G61 ROI Intensity Ablation

 01 ROI intensity left
 02 ROI intensity right

 Attributes of
01 ROI intensity left

Verbosity level
None

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.

 Attributes of
02 ROI intensity right

Verbosity level
None

Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.




■ **Measured values for plotter**

591	0 ... 255	Intensity ablation left
592	0 ... 255	Intensity ablation right
593	0 ... xxx	NoAblation size left
594	0 ... xxx	NoAblation size right

■ **Subgraphs interface**

IN bridges

OUT bridges

 image	Img	 value	Ablation intensity left Ablation intensity right
 value	Seam pos left filtered Seam pos right filtered ROI grey valid ROI ablation Y ROI ablation H		

- **Graph block diagram**

