

# 5 - S35 CALC Geometry Ablation - Cavvex inside

## Description

Calculate the seam geometry measurements width and roundness. Concav, convex and mismatch is calculated with the "Reference" inside the ablation area.


### Icon



#### 5 S35 CALC Geometry Ablation - Cavvex inside


Calculate the seam geometry measurements width and roundness. Mismatch is calculated outside the ablation borders. Concav, convex is calculated inside the ablation borders

#### Parameters






Parameter	Comment
Number	Min. angle of the laser line shape to set a "seam border". [Degree]



Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Filter length	To define a reference position the vertical positions of the found laser line shape are averaged over "Filter length" pixel. [Pixel]

# Verbosity example:

The magenta rectangle shows the centered laser line ROI. The red line on the laser line shows the shape from the laser line tracking.







Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.




Parameter	Comment
Number	Number of pixels to shift the found left seam border leftwards, and the found right seam border rightwards to set the start/end point of the range where to check for 'concavity/convexity/mismatch'.  [Pixel]



Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Length	Number of points on the laser line shape, starting at the "shifted" left seam border leftwards, to fit a straight line for the "laser line part on left blank". [Pixel]
Fit horizontal	If active, the left side "Reference" line is expected/searched to be horizontal.

## Verbosity example:

The magenta rectangle shows the centered laser line ROI. The red line shows the fitted straight line on the left side. The two green crosses mark the (horizontal) range where the line fit was made.






Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Length	Number of points on the laser line shape, starting at the "shifted" right seam border rightwards, to fit a straight line for the "laser line part on right blank". [Pixel]
Fit horizontal	If active, the right side "Reference" line is expected/searched to be horizontal.

# Verbosity example:

The magenta rectangle shows the centered laser line ROI. The red line shows the fitted straight line on the right side. The two green crosses mark the (horizontal) range where the line fit was made.







Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.




Parameter	Comment
Number	Number of pixels to shift the found left ablation border leftwards, and the found right ablation border rightwards to set the start point for the "laser line part on blank".  [Pixel]




Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Length	Number of points on the laser line shape, starting at the "shifted" left ablation border leftwards, to fit a straight line for the "laser line part on left blank".  [Pixel]
Fit horizontal	If active, the left side "Reference" line is expected/searched to be horizontal.

## Verbosity example:

The magenta rectangle shows the centered laser line ROI. The red line shows the fitted straight line on the left side. The two green crosses mark the (horizontal) range where the line fit was made.






Parameter	Comment
Verbosity level	Selection of verbosity level. Larger verbosity levels offer more overlay information.
Length	Number of points on the laser line shape, starting at the "shifted" right ablation border rightwards, to fit a straight line for the "laser line part on right blank". [Pixel]
Fit horizontal	If active, the right side "Reference" line is expected/searched to be horizontal.

### Verbosity example:

The magenta rectangle shows the centered laser line ROI. The red line shows the fitted straight line on the right side. The two green crosses mark the (horizontal) range where the line fit was made.







Parameter	Comment
Filter length	Number of camera images to average the measured seam width values. [Images].



Parameter	Comment
Filter length	Number of camera images to average the measured blank mismatch values. [Images].



Parameter	Comment	
Filter length	Number of camera images to average the measured convexity values. [Images].	



Parameter	Comment	
Filter length	Number of camera images to average the measured concavity values. [Images].	



Parameter	Comment
Filter length	Number of camera images to average the measured <i>positive</i> seam roundness values. [Images].



Parameter	Comment
Filter length	Number of camera images to average the measured <i>negative</i> seam roundness values. [Images].



Parameter	Comment
Number	Only tracked laser line points with this min. intensity are real laser line points. [Greylevel].



# Measured values for plotter

556	0/1	Plausibility GEO error
572	0 255	Intensity Line
703	0 xxx	Seam width
709	-xxx +xxx	Height difference
711	0 xxx	Concavity
712	0 xxx	Convexity
713	0 xxx	Roundness pos.
714	0 xxx	Roundness neg.

# ■ Subgraphs interface

# IN bridges OUT bridges

<b>■</b> image	Img	<b></b> ∨alue	PlausError line
■ Line ■ value	Line  Seam pos left filtered  Seam pos right filtered  Start end active  Line intensity  ROI line valid  Ablation out X left  Ablation out X right	value	Seam width Seam roundness pos Seam roundness neg Seam concav Seam convex Seam height diff

# ■ Graph block diagram

